

M&E System Application to monitor & evaluate the Participatory Irrigation Management (PIM) and Irrigation Management Transfer (IMT) Process

1.6 Installation Demo per level and Testing of the remotely installed systems: the alpha version


Activity implemented in collaboration with CIHEAM/IAM Bari

The Demo per National, Regional and Local level

National Level

Depending on the hierarchical level concerned, the program to install is different: Adobe Acrobat for WUAs computers and Microsoft Access Runtime 2010 for the regional and national levels computers

Regional Level




Local Level

Local Level

Local Level


Local Level




Data Request per level, and Data aggregation and Applicability concepts

If some computers of the local units haven't Adobe Acrobat installed, it can be downloaded from the Adobe website get.adobe.com/uk/reader/, installed and used to open the file to be compiled







Prerequisites per level and per platform

The advantage of this system is to have very low requirements at the local level: no software license at any level, with very low system requirements, probably already present in the offices

LOCAL LEVEL REGIONAL LEVEL NATIONAL LEVEL To fill out the simple PDF form, the The system requirements to use the selected The system requirements to use the selected requirements are a Personal Computer running database management software, are as follows: database management software, are as follows: Windows or Mac or Linux Operating System, with the only feature to be able to run Adobe 1 gigahertz (Ghz) or faster x86- or x64-bit 1 gigahertz (Ghz) or faster x86- or x64-bit Acrobat Reader 9 or later versions. processor with SSE2 instruction set processor with SSE2 instruction set Required operating system: Windows 8, • Required operating system: Windows 8, Windows 7, Windows Server 2008 R2 or Windows 7, Windows Server 2008 R2 or Windows Server 2012 Windows Server 2012 Required memory: 1 GB of RAM (32 bit); • Required memory: 1 GB of RAM (32 bit); 2 GB of RAM (64 bit) 2 GB of RAM (64 bit) 3 GB of available hard-disk space 3 GB of available hard-disk space Graphics hardware acceleration requires • Graphics hardware acceleration requires a DirectX 10 graphics card and 1024 x 576 a DirectX 10 graphics card and 1024 x 576 resolution resolution Required .NET version: 3.5, 4.0 o 4.5 Required .NET version: 3.5, 4.0 o 4.5 Microsoft Access Runtime 2010 Microsoft Access Runtime 2010

INSTALLATION OF THE ALPHA VERSION


Double-click the file AccessRuntime.exe on your hard disk to start the setup program. Follow the onscreen instructions to complete the installation.

Install also the Service Pack for Microsoft Access Runtime 2010: also here, follow the onscreen instructions to complete the installation.

At the end of these installation processes, you will be able to install the MEVS application. Follow the onscreen instructions to complete the installation: at the end you'll find the icon shortcut.


Double-click on that shortcut and execute the application, without any license of Microsoft Access








Please, pay attention: you have to give the rights to use the application: it depends on the operating system you are using, but in some cases you have to give the complete control rights to





You can now select the section of the software in which the data should be inputed, and then proceed, following the Access input method, by clicking over the buttons and writing in the fields you have to compile.